TejRajAlgo

Getting started: your account, step by step.

Everything you need to go from signing up to watching your own strategies trade live — creating your login, turning on two-factor security with Microsoft Authenticator, connecting your Angel One account, and whitelisting your trading server's IP.

① Create & verify
② Secure with 2FA
③ Get activated
④ Connect Angel
⑤ Whitelist IP
⑥ Go live

User Onboarding Guide · tejrajalgo.com · v1.0 · November 2026

OVERVIEW

The journey at a glance

Six steps take you from a brand-new sign-up to a live, read-only view of your own strategies. Steps 1, 2 and 4 are quick; your admin handles activation in between; and the IP whitelisting (step 5) is the one broker step that lets real orders reach your account.

1. **Create your account & verify your email**
   Sign up at tejrajalgo.com with your email and a password, then click the link we email you.

2. **Turn on two-factor security (Microsoft Authenticator)**
   Add a 6-digit authenticator code — required before you can be activated. Face ID / PIN optional too.

3. **Your admin activates your account**
   Until then you're in a safe “pending” state — you can set everything up, but no strategies run yet.

4. **Connect your Angel One account**
   Enter your Angel SmartAPI details once; they're encrypted and used only to place your trades.

5. **Whitelist your trading server's static IP in Angel**
   Your admin gives you a fixed IP; you add it to your Angel SmartAPI app so your orders are accepted.


6. **Watch your dashboard — live**
   Your strategies, positions and P&L appear automatically, refreshing every few seconds.

> **A quick reassurance:** your account stays in a safe, read-only state the whole way through. Nothing can place a real order until your admin has activated you *and* your Angel account + IP are connected — so there's no way to accidentally trade while you're still setting up.

1 Create your account & verify your email

Your login is just an email and a password — nothing to do with your Angel account yet. You'll confirm your email with a one-time link before your first sign-in.

1. Go to **tejrajalgo.com** and click **Create account**.
2. Enter your **email** and a **password** (at least 10 characters). Use a strong, unique password.
3. Click **Create account**. You'll see a “Check your email” screen.
4. Open the email from TejRajAlgo and click the **verification link**. (No email after a minute? Check your spam folder — the first message from a new sender sometimes lands there.)
5. You're verified. Head back to the site to sign in.




The sign-up screen at tejrajalgo.com

> **Why a password *and* 2FA later?** The password gets you in; the second factor (next step) is what protects real money. We never store your password in a readable form, and no one — not even your admin — can see it.

2 Turn on two-factor security

A second factor means even someone with your password can't get in. We recommend **Microsoft Authenticator** — a free app that shows a 6-digit code that changes every 30 seconds. **This is required** before your admin can activate your account.

1. On your phone, install **Microsoft Authenticator** from the App Store or Google Play. (Google Authenticator or Authy also work.)
2. Sign in to **tejrajalgo.com**. On your dashboard, find **Two-factor authentication** and tap **Set up authenticator**.
3. In Microsoft Authenticator: tap **+** → **Other account** → **Scan a QR code**, and scan the code on screen.
4. Can't scan? Choose **"enter code manually"** in the app and type the setup key shown under the QR.
5. The app now shows a 6-digit code for **TejRajAlgo**. Type that code into the dashboard and tap **Confirm & turn on**.
6. Done — your 2FA badge turns **ON**. From now on, signing in with your password also asks for the current code.




Scan the QR, then confirm the 6-digit code

> **Prefer a one-tap sign-in?** You can also add a **passkey** (Face ID / fingerprint) or a **6-digit device PIN** from the same dashboard. Any one of these counts as your second factor — but an authenticator app is the most portable across devices.

3 Your admin activates your account

New accounts don't get the live product straight away. After you've set up a second factor, your admin reviews and **approves** you. Until then you're in a safe **pending** state — you can see your account and set everything up, but no strategies run.

- Right after you sign in you'll see an amber **"Account pending activation"** banner. That's normal.
- You can still do everything else — connect Angel, add a passkey — while you wait.
- Your admin can only approve you once your **2FA is on** (that's the rule that keeps real money safe), so finish Step 2 first.
- Once approved, the banner turns green and your **live dashboard** appears automatically — no need to sign in again.



Pending → approved, once your admin activates you


Why the gate? It guarantees that no account can ever reach real-money trading protected by only a password. Approval needs a second factor, every time.

4 Connect your Angel One account

This is how your engine places trades **on your own Angel account**. You enter your Angel SmartAPI details once; they're **encrypted** the moment you save them and are never shown back on screen.

1. From your dashboard, open **Connect Angel**.
2. Enter your Angel **SmartAPI key**, **Client code**, **MPIN**, and your **TOTP secret** (the authenticator key from your Angel SmartAPI app).
3. Click **Connect**. The screen shows a masked confirmation (e.g. **A***45**) — the real values are stored encrypted.
4. Your engine will log in to Angel automatically each morning; you won't re-enter anything.

Keep these private. Your MPIN and TOTP secret are the keys to your brokerage account. Only ever enter them on tejrajalgo.com's Connect Angel screen — never share them in chat, email, or screenshots.




Entered once, stored encrypted

5 Whitelist your static IP in Angel

Your strategies run on a **dedicated server** that's yours alone, with its own fixed **static IP address**. Angel One (per SEBI rules, effective 1 April 2026) only accepts API orders coming from an IP you've registered — so your server's IP must be whitelisted in your Angel SmartAPI app, or no orders go through.

The process, end to end (for every new user)

1. After activating you, your **admin provisions your dedicated engine** and gives you its **static IP address** (for example **13.201.xx.xx**). You'll get this from your admin.
2. Log in to the Angel **SmartAPI developer portal** at **smartapi.angelone.in** (this is separate from the normal Angel One trading app).
3. Open **My Apps** and select the API app whose key you connected in Step 4.
4. Go to the **IP whitelist / IP settings** section.
5. Enter the static IP your admin gave you — the **bare address only**, no `http://`, no port, no spaces — and click **Submit**. It takes effect immediately.
6. Tell your admin it's done. Your engine can now place orders on your account.




Angel SmartAPI → My Apps → IP whitelist

1 IP ↔ 1 client	A static IP maps to one client at a time. Your app can hold a primary plus an optional backup IP.
Change ≤ 1×/week	You can update your mapped IP at most once per calendar week — so don't change it casually.
Family sharing	SEBI-defined family members can share an IP only with a formal written request + 2FA to the broker.
From 1 Apr 2026	Orders from any non-whitelisted IP are rejected — so this step is what lets real trades reach your account.

Already whitelisted? If you've added your static IP before (as Pavan has), you're set — there's nothing to redo unless your engine's IP ever changes, in which case your admin will give you the new one to whitelist.

6 Your live dashboard

Once you're activated and connected, your dashboard shows your own strategies working in real time — **read-only**, refreshing every few seconds. Starting, stopping and any real-money settings are managed by your admin; you watch and track.



Your read-only live view — strategies, positions and P&L

Signing in next time

- Your 6-digit **authenticator code** is asked alongside your password each time.
- Set up a **passkey (Face ID / fingerprint)** or a **device PIN** once, and future sign-ins on that device are one tap — no password typing.

REFERENCE

Quick help

No verification email	Check your spam / junk folder — the first message from a new sender often lands there. Mark it “Not spam” and the link will work.
Can't be approved yet	Your admin can only approve you after your 2FA is on. Finish Step 2 (authenticator, passkey, or PIN), then tell your admin.
Lost your phone / app	Use “Forgot password” to regain access, then re-set your authenticator. If a passkey or PIN was on another device, use that device.
Orders rejected by Angel	Almost always the static IP isn't whitelisted, or it changed. Confirm the IP your admin gave you is in Angel SmartAPI → My Apps → IP whitelist.
Dashboard says “reconnecting”	A brief blip reaching your engine — it recovers on its own. If it persists, let your admin know.
Your data is yours	You only ever see your own account. Your password is stored one-way (never readable), and your Angel secrets are encrypted.

Need a hand? Reach out to your admin (the master account) — they can see your account's status, re-send activation, and help with the Angel connection or IP whitelisting.



TejRajAlgo.com